

```
*****
*                                     *
*                               Row - Coloring                               *
*****
```

REPORT zdemo_alv4.

```
*****
*                               Type - Pools                               *
*****
```

TYPE-POOLS slis.

```
*****
*                               Data type                                 *
*****
```

```
TYPES : BEGIN OF ty_ekko,
        lifnr TYPE ekko-lifnr,
        aedat TYPE erdat,
        ebeln TYPE ebeln,
        clr_row(4) TYPE c,
        END OF ty_ekko.
```

TYPES ty_t_ekko TYPE TABLE OF ty_ekko.

```
*****
*                               Constants                                 *
*****
```

CONSTANTS c_check type c value 'X'.

```
DATA : it_ekko TYPE ty_t_ekko,
        it_fieldcat TYPE slis_t_fieldcat_alv,
        wa_fieldcat TYPE slis_fieldcat_alv,
        is_layout TYPE slis_layout_alv,
        wa_ekko TYPE ty_ekko,
        v_lifnr TYPE lifnr.
```

```
*****
```

* *Select-Options* *

SELECT-OPTIONS s_lifnr FOR v_lifnr DEFAULT 1000 TO 1100.

* *START-OF-SELECTION.* *

START-OF-SELECTION.

SELECT lifnr aedat ebeln INTO TABLE it_ekko FROM ekko W
HERE lifnr IN s_lifnr.

* *END-OF-SELECTION.* *

END-OF-SELECTION.

CLEAR wa_fieldcat.
wa_fieldcat-fieldname = ' LIFNR'.
wa_fieldcat-col_pos = 1.
wa_fieldcat-seltext_m = 'Vendor'.
wa_fieldcat-key = c_check.
APPEND wa_fieldcat TO it_fieldcat.

CLEAR wa_fieldcat.
wa_fieldcat-fieldname = ' EBELN'.
wa_fieldcat-col_pos = 2.
wa_fieldcat-seltext_m = 'Po. No.'.
APPEND wa_fieldcat TO it_fieldcat.

CLEAR wa_fieldcat.
wa_fieldcat-fieldname = ' LIFNR'.
wa_fieldcat-col_pos = 3.
wa_fieldcat-seltext_m = 'Vendor'.
APPEND wa_fieldcat TO it_fieldcat.

```
*           is_layout           *  
*****
```

```
is_layout-info_fieldname = 'CLR_ROW'.
```

```
CLEAR wa_ekko.  
      wa_ekko-clr_row = 'C711'.
```

```
*****  
*           MODIFY           *  
*****
```

```
MODIFY it_ekko FROM wa_ekko TRANSPORTING clr_row whe  
re  ebeln = '3005000281'.
```

```
*****  
*  REUSE_ALV_GRID_DISPLAY  *  
*****
```

```
CALL FUNCTION 'REUSE_ALV_GRID_DISPLAY'  
EXPORTING  
      is_layout = is_layout  
      it_fieldcat = it_fieldcat  
TABLES  
      t_outtab = it_ekko.
```



List Edit Goto Views Settings System Help



alv 6



Ven No.	Po. No..	Cret. Dt.	Priority
0000005550	3000000004	02.11.2000	H
0000005550	3000000005	02.11.2000	H
0000003020	3000000006	02.11.2000	M
0000003730	3000000007	02.11.2000	M
0000003910	3000000008	02.11.2000	L
0000003411	3000000009	02.11.2000	L
0000003411	3000000010	02.11.2000	H
0000003730	3000000011	02.11.2000	L

EC

Start



sapmmc



ABAP Editor: Change Re...



alv 6



ALV